



Our Example Architecture

Main
Memory



...



Our Example Architecture

Main
Memory


00000							
00001							
00010							
00011							
00100							
00101							
00110							
00111							
01000							
01001							

...


11110							
11111							

Our Example Architecture

Central Processing Unit



Main Memory




Woody's Machine Language

Assembly Language Instruction	Machine Language Instruction
CopyFrom	000
CopyTo	001
Add	010
Subtract	011
Read	100
Print	101
IfNegGoTo	110
Stop	111


Program Execution

Our Hypothetical Computer




Our Hypothetical Computer

- Word size: 8 bits (1 byte)




Our Hypothetical Computer

- Word size: 8 bits (1 byte)
- Number of instructions: 8




Our Hypothetical Computer

- Word size: 8 bits (1 byte)
- Number of instructions: 8
 - To represent $2^3 = 8$ total instructions, **need 3 bits**




Our Hypothetical Computer

- Word size: 8 bits (1 byte)
- Number of instructions: 8
 - To represent $2^3 = 8$ total instructions, need 3 bits
 - Leaves **5 bits** to represent addresses



Our Hypothetical Computer

- Word size: 8 bits (1 byte)
- Number of instructions: 8
 - To represent $2^3 = 8$ total instructions, need 3 bits
 - Leaves 5 bits to represent addresses
- 5 bits for addresses: $2^5 = 32$ memory cells →



Eight Machine Language Instructions

Instruction Code	Meaning of the Instruction
000	Copy word from <u>memory address</u> into DR
001	Copy word to <u>memory address</u> from DR
010	Add word in <u>memory address</u> to word in DR
011	Subtract word in <u>memory address</u> from word in DR
100	Read word from input into DR
101	Print word in DR to output
110	<i>Conditional execution</i> : If word in DR is negative, copy a new <u>memory address</u> into PC
111	Stop execution

Underline: an argument (value) required by that instruction

Example of an Instruction

00110110

one word
(here, one byte)

Code	Meaning of the Instruction
000	Copy from <u>address</u> into DR
001	Copy to <u>address</u> from DR
010	Add word in <u>address</u> to DR
011	Subtract word in <u>address</u> from DR
100	Read from input into DR
101	Print to output from DR
110	If DR is < 0, copy <u>address</u> into PC
111	Stop execution

Example of an Instruction

00110110




Instruction
code

Code	Meaning of the Instruction
000	Copy from <u>address</u> into DR
001	Copy to <u>address</u> from DR
010	Add word in <u>address</u> to DR
011	Subtract word in <u>address</u> from DR
100	Read from input into DR
101	Print to output from DR
110	If DR is < 0, copy <u>address</u> into PC
111	Stop execution

Example of an Instruction

00110110

Argument
(memory address)




Code	Meaning of the Instruction
000	Copy from <u>address</u> into DR
001	Copy to <u>address</u> from DR
010	Add word in <u>address</u> to DR
011	Subtract word in <u>address</u> from DR
100	Read from input into DR
101	Print to output from DR
110	If DR is < 0, copy <u>address</u> into PC
111	Stop execution

Example of an Instruction

00110110

Decoding the Instruction:



Code	Meaning of the Instruction
000	Copy from <u>address</u> into DR
001	Copy to <u>address</u> from DR
010	Add word in <u>address</u> to DR
011	Subtract word in <u>address</u> from DR
100	Read from input into DR
101	Print to output from DR
110	If DR is < 0, copy <u>address</u> into PC
111	Stop execution

Example of an Instruction

00110110

Decoding the Instruction:

Copy to ...



Code	Meaning of the Instruction
000	Copy from <u>address</u> into DR
001	Copy to <u>address</u> from DR
010	Add word in <u>address</u> to DR
011	Subtract word in <u>address</u> from DR
100	Read from input into DR
101	Print to output from DR
110	If DR is < 0, copy <u>address</u> into PC
111	Stop execution

Example of an Instruction

00110110

Decoding the Instruction:

Copy to ...

Code	Meaning of the Instruction
000	Copy from <u>address</u> into DR
001	Copy to <u>address</u> from DR
010	Add word in <u>address</u> to DR
011	Subtract word in <u>address</u> from DR
100	Read from input into DR
101	Print to output from DR
110	If DR is < 0, copy <u>address</u> into PC
111	Stop execution

Example of an Instruction

00110110

Decoding the Instruction:

Copy to **address 10110**...

Code	Meaning of the Instruction
000	Copy from <u>address</u> into DR
001	Copy to address from DR
010	Add word in <u>address</u> to DR
011	Subtract word in <u>address</u> from DR
100	Read from input into DR
101	Print to output from DR
110	If DR is < 0, copy <u>address</u> into PC
111	Stop execution

Example of an Instruction

00110110

Decoding the Instruction:

Copy to address 10110
from DR

This instruction copies the
contents of the data register
into memory cell addressed
 $10110_2 = 22_{10}$

Code	Meaning of the Instruction
000	Copy from <u>address</u> into DR
001	Copy to <u>address</u> from DR
010	Add word in <u>address</u> to DR
011	Subtract word in <u>address</u> from DR
100	Read from input into DR
101	Print to output from DR
110	If DR is < 0, copy <u>address</u> into PC
111	Stop execution

Example of an Instruction

10000000

Decoding the Instruction:

Read from input...

Code	Meaning of the Instruction
000	Copy from <u>address</u> into DR
001	Copy to <u>address</u> from DR
010	Add word in <u>address</u> to DR
011	Subtract word in <u>address</u> from DR
100	Read from input into DR
101	Print to output from DR
110	If DR is < 0, copy <u>address</u> into PC
111	Stop execution

Example of an Instruction

10000000

Decoding the Instruction:

Read from input...

No argument...

Code	Meaning of the Instruction
000	Copy from <u>address</u> into DR
001	Copy to <u>address</u> from DR
010	Add word in <u>address</u> to DR
011	Subtract word in <u>address</u> from DR
100	Read from input into DR
101	Print to output from DR
110	If DR is < 0, copy <u>address</u> into PC
111	Stop execution


Example of an Instruction

10000000

Decoding the Instruction:

Read from input...

No argument,
hence zeros
(to fill the byte)



Code	Meaning of the Instruction
000	Copy from <u>address</u> into DR
001	Copy to <u>address</u> from DR
010	Add word in <u>address</u> to DR
011	Subtract word in <u>address</u> from DR
100	Read from input into DR
101	Print to output from DR
110	If DR is < 0, copy <u>address</u> into PC
111	Stop execution

Example of an Instruction

10000000

Decoding the Instruction:

Read from input into DR

This instruction copies a word from the input unit into the data register


Code	Meaning of the Instruction
000	Copy from <u>address</u> into DR
001	Copy to <u>address</u> from DR
010	Add word in <u>address</u> to DR
011	Subtract word in <u>address</u> from DR
100	Read from input into DR
101	Print to output from DR
110	If DR is < 0, copy <u>address</u> into PC
111	Stop execution

Preparing To Execute a Program


- 🌍 Your program is first written in a *high-level language* (e.g., Java): source code
- 🌍 Converted into *machine language*: executable
- 🌍 To run, executable is copied into main memory
- 🌍 PC is loaded with the memory address of the first instruction in the executable

Fetch-Execute Cycle


1. Copy the word referred to by the PC into the IR (i.e., *fetch*)
2. Increment the address stored in the PC
3. Decode & *execute* the contents of the IR
4. Unless a stop instruction, goto step 1




Initial state of memory after loading program and setting PC to 00000



1. Copy word referred to by PC into Instruction Register



1. Copy word referred to by PC into Instruction Register



1. Copy word referred to by PC into Instruction Register

CPU

Instruction
Register

00001001

Program
Counter

00001

Data
Register

Input Unit

Output Unit

Main Memory

00000	00001001	10000	00000000
00001	11000101	10001	00000000
00010	00001010	10010	00000000
00011	01001011	10011	00000000
00100	11100000	10100	00000000
00101	00001010	10101	00000000
00110	01101100	10110	00000000
00111	00101010	10111	00000000
01000	11100000	11000	00000000
01001	10000001	11001	00000000
01010	00000110	11010	00000000
01011	00000100	11011	00000000
01100	00000001	11100	00000000
01101	00000000	11101	00000000
01110	00000000	11110	00000000
01111	00000000	11111	00000000

2. Increment the Program Counter

CPU

Main Memory

Instruction
Register

00001001

Program
Counter

00001

Data
Register

Input Unit

Output Unit

00000

00001001

10000

00000000

00001

11000101

10001

00000000

00010

00001010

10010

00000000

00011

01001011

10011

00000000

00100

11100000

10100

00000000

00101

00001010

10101

00000000

00110

01101100

10110

00000000

00111

00101010

10111

00000000

01000

11100000

11000

00000000

01001

10000001

11001

00000000

01010

00000110

11010

00000000

01011

00000100

11011

00000000

01100

00000001

11100

00000000

01101

00000000

11101

00000000

01110

00000000

11110

00000000


01111

00000000


11111

00000000


3. Decode and Execute instruction




3. Decode and Execute instruction – 000 is op code for CopyFrom



3. Decode and Execute instruction – 01001 is address to copy from



3. Decode and Execute instruction – 01001 contains a word



3. Decode and Execute instruction – Instruction execution is complete

CPU

Main Memory

Instruction Register	Program Counter
00001001	00001
Data Register	
10000001	

Input Unit	Output Unit

00000	00001001	CopyFrom	10000	00000000
00001	11000101		10001	00000000
00010	00001010		10010	00000000
00011	01001011		10011	00000000
00100	11100000		10100	00000000
00101	00001010		10101	00000000
00110	01101100		10110	00000000
00111	00101010		10111	00000000
01000	11100000		11000	00000000
01001	10000001		11001	00000000
01010	00000110		11010	00000000
01011	00000100		11011	00000000
01100	00000001		11100	00000000
01101	00000000		11101	00000000
01110	00000000		11110	00000000
01111	00000000		11111	00000000

Repeat: 1. Copy word referred to by PC to IR

CPU

Instruction
Register

11000101

Program
Counter

00001

Data
Register

10000001

Input Unit

Output Unit

Main Memory

00000	00001001	CopyFrom	10000	00000000
00001	11000101		10001	00000000
00010	00001010		10010	00000000
00011	01001011		10011	00000000
00100	11100000		10100	00000000
00101	00001010		10101	00000000
00110	01101100		10110	00000000
00111	00101010		10111	00000000
01000	11100000		11000	00000000
01001	10000001		11001	00000000
01010	00000110		11010	00000000
01011	00000100		11011	00000000
01100	00000001		11100	00000000
01101	00000000		11101	00000000
01110	00000000		11110	00000000
01111	00000000		11111	00000000

Repeat: 1. Copy word referred to by PC to IR

CPU

Instruction
Register

11000101

Program
Counter

00010

Data
Register

10000001


Input Unit


Output Unit

Main Memory


00000	00001001	CopyFrom	10000	00000000
00001	11000101		10001	00000000
00010	00001010		10010	00000000
00011	01001011		10011	00000000
00100	11100000		10100	00000000
00101	00001010		10101	00000000
00110	01101100		10110	00000000
00111	00101010		10111	00000000
01000	11100000		11000	00000000
01001	10000001		11001	00000000
01010	00000110		11010	00000000
01011	00000100		11011	00000000
01100	00000001		11100	00000000
01101	00000000		11101	00000000
01110	00000000		11110	00000000
01111	00000000		11111	00000000

2. Increment PC







3. Decode and execute instruction – 110 is the op code for IfNegGoTo




3. Decode and execute instruction – Check value in data register




3. Decode and execute instruction – DR value is -1




3. Decode and execute instruction – Copy rightmost 5 bits of IR to PC



3. Decode and execute instruction – execution is complete



1. Copy word referred to by PC to IR



1. Copy word referred to by PC to IR

CPU

Instruction
Register

00001010

Program
Counter

00110

Data
Register

10000001


Input Unit


Output Unit

Main Memory


00000	00001001	CopyFrom	10000	00000000
00001	11000101	IfNegGoTo	10001	00000000
00010	00001010		10010	00000000
00011	01001011		10011	00000000
00100	11100000		10100	00000000
00101	00001010		10101	00000000
00110	01101100		10110	00000000
00111	00101010		10111	00000000
01000	11100000		11000	00000000
01001	10000001		11001	00000000
01010	00000110		11010	00000000
01011	00000100		11011	00000000
01100	00000001		11100	00000000
01101	00000000		11101	00000000
01110	00000000		11110	00000000
01111	00000000		11111	00000000

2. Increment PC







3. Decode and execute instruction – 000 is op code for CopyFrom




3. Decode and execute instruction



3. Decode and execute instruction – copy value to DR. Execution complete.



1. Copy word referred to by PC to IR.



1. Copy word referred to by PC to IR.

CPU

Main Memory

Instruction Register

01101100

Program Counter

00111

Data Register


00000110

Input Unit


Output Unit

00000	00001001	CopyFrom	10000	00000000
00001	11000101	IfNegGoTo	10001	00000000
00010	00001010		10010	00000000
00011	01001011		10011	00000000
00100	11100000		10100	00000000
00101	00001010	CopyFrom	10101	00000000
00110	01101100		10110	00000000
00111	00101010		10111	00000000
01000	11100000		11000	00000000
01001	10000001		11001	00000000
01010	00000110		11010	00000000
01011	00000100		11011	00000000
01100	00000001		11100	00000000
01101	00000000		11101	00000000
01110	00000000		11110	00000000
01111	00000000		11111	00000000


2. Increment PC




3. Decode and execute instruction




3. Decode and execute instruction – 011 is Subtract




3. Decode and execute instruction – data register is first operand




3. Decode and execute instruction – word at 01100 is second operand




3. Decode and execute instruction – word at 01100 is second operand






3. Decode and execute instruction: $5_{10} = 00000101_2$. Result is stored in DR.



1. Copy word referred to by PC to IR.



1. Copy word referred to by PC to IR.

CPU

Main Memory

Instruction Register

00101010

Program Counter

01000

Data Register


00000101

Input Unit


Output Unit

00000	00001001	CopyFrom	10000	00000000
00001	11000101	IfNegGoTo	10001	00000000
00010	00001010		10010	00000000
00011	01001011		10011	00000000
00100	11100000		10100	00000000
00101	00001010	CopyFrom	10101	00000000
00110	01101100	Subtract	10110	00000000
00111	00101010		10111	00000000
01000	11100000		11000	00000000
01001	10000001		11001	00000000
01010	00000110		11010	00000000
01011	00000100		11011	00000000
01100	00000001		11100	00000000
01101	00000000		11101	00000000
01110	00000000		11110	00000000
01111	00000000		11111	00000000


2. Increment PC




3. Decode and execute instruction




3. Decode and execute instruction – 001 is CopyTo




3. Decode and execute instruction – 01010 is target location



3. Decode and execute instruction – value in DR copied to memory



1. Copy word referred to by PC to IR



1. Copy word referred to by PC to IR

CPU

Main Memory

Instruction Register

11100000

Program Counter

01001

Data Register


00000101

Input Unit


Output Unit

00000	00001001	CopyFrom	10000	00000000
00001	11000101	IfNegGoTo	10001	00000000
00010	00001010		10010	00000000
00011	01001011		10011	00000000
00100	11100000		10100	00000000
00101	00001010	CopyFrom	10101	00000000
00110	01101100	Subtract	10110	00000000
00111	00101010	CopyTo	10111	00000000
01000	11100000		11000	00000000
01001	10000001		11001	00000000
01010	00000101		11010	00000000
01011	00000100		11011	00000000
01100	00000001		11100	00000000
01101	00000000		11101	00000000
01110	00000000		11110	00000000
01111	00000000		11111	00000000


2. Increment PC



3. Decode and execute instruction




3. Decode and execute instruction – 111 is op code for Stop



Stored Program Concept: Instructions & data together in main memory

- CPU “knows” difference based *only* on execution process

Possible Overflow

 Using our 1-byte word limit and sign magnitude, add the numbers:


$$01100110_2 + 00011011_2$$

Possible Overflow

 Using our 1-byte word limit and sign magnitude, add the numbers:

$$\begin{aligned} & 01100110_2 + 00011011_2 \\ & = 102_{10} + 27_{10} = 129_{10} \\ & = 10000001_2 \end{aligned}$$

Possible Overflow

 Using our 1-byte word limit and sign magnitude, add the numbers:

$$01100110_2 + 00011011_2$$

$$= 102_{10} + 27_{10} = 129_{10}$$

$$= 10000001_2$$


sign bit (indicating negative)

Possible Overflow

 Using our 1-byte word limit and sign magnitude, add the numbers:

$$\begin{aligned} & 01100110_2 + 00011011_2 \\ & = 102_{10} + 27_{10} = 129_{10} \\ & = 10000001_2 \end{aligned}$$

 So computer would report -1 as the answer!

 Overflow: too few bits to represent the result